

Connection to a Network license



1/ Installation of Phase Manager

Donwload Phase Manager (click here for last release). **Right click** on the executable than run it with **Administrator rights**

Once launched, choose the installation language:



Skip the welcome screen by clicking on Next:



Read then accept the license agreement to continue the installation by clicking on Next :

📽 Setup - Phase Manager X.x —	×
License Agreement Please read the following important information before continuing.	
Please read the following License Agreement. You must accept the terms of this agreement before continuing with the installation.	
LICENSE OF USE SOFTWARE PHASE MANAGER Article 1 - Purpose of these terms and conditions The purpose of these general terms and conditions is to specify the conditions under which the PROJET LINEAIRE DEVELOPPEMENT EDITOR grants the USER a right to use the PHASE MANAGER SOFTWARE and ensures the maintenance of the said PHASE MANAGER SOFTWARE. Article 2 - Use of the PHASE MANAGER SOFTWARE The PHASE MANAGER SOFTWARE is for experienced or non-confirmed users working on a Windows environment only (Vista or higher). The USER tested the PHASE MANAGER SOFTWARE before signing the purchase order.	~
I accept the agreement I do not accept the agreement	
< Back Next > 0	Cancel

By default the setup will ask you to install Phase Manager in : C:\Program Files (x86)\PhaseManager X If you didn't launch it with admin right, it will propose you to install Phase Manager in :

C:\Users\Public\Documents\PhaseManager7

💐 Setup - Phase Manager 🗙 🗙	_		×
Select Destination Location Where should Phase Manager be installed?			
Setup will install Phase Manager X.x into the following folde	r.		
To continue, click Next. If you would like to select a different folder,	click E	Browse.	
C:\Program Files (x86)\PhaseManager X.x		Browse	
At least 848,7 MB of free disk space is required.			
< Back Nex	t >		Cancel

Choose 'Single user installation'

Select Components Which components should be installed?			
Select the components you want to inst install. Click Next when you are ready t	tall; clear the compone to continue.	ents you do not v	vant to
Single user installation			\sim
	< Back	Next >	Cancel

Validate the Start Menu Folder screen by clicking on Next :



Select Star Where s	rt Menu Folder hould Setup place the program's shortcuts?	
<u> </u>	tup will create the program's shortcuts in the follow	wing Start Menu folder.
To conti	nue, click Next. If you would like to select a differen	nt folder, click Browse.
Projet L	ineaire	Browse

Choose and validate the icons creation screen by clicking Next:

Select the additional tasks you would like Setup to perform while installing Phase Manager $X.x$, then click Next.
Additional icons:
Create a desktop icon
Create a Quick Launch icon

On the following screen click on Install then once installation is complete, click on Finish

2/ Connection to the network license

Once Phase Manager is installed, double-click on its icon to launch it. At first launch, the license configurator will display:

To connect to your network license, you will need to fill in the following fields:

4/6



🗞 Phase Manager Launcher		- 0	×
Licence System Java System			
		Licensing Configuration	
Phase Manager	Module	Reseau 👻	
Scheduled construction PHASE MAPS	Product ID	LPMP your product ID	
Licence	Activation Key	Your activation key (serial number)	
& Licensing	Create new licen	ce Choose a licence 💿	
Configuration	Browse	the same path on server used for activation	
Settings			
	L		
		L	aunch

Module

Choose Network | Réseau:

FYI : If you want to test Phase Manager for 14 days, choose 'Demo'.

Product ID

Fill in the Product ID that's been sent to you by Projet Linéaire:

- licence pattern : LPMM-00NNN0 X 00abcDEF (NNN is the number of your license, and X the version)
- only paste the right part of your Product-ID, after the '-'

Activation key

Fill in the Serial number sent to you by Projet Linéaire or reseller.

Licence

Tick "Choose a licence", then indicate the location of the license file: Indicate its UNC path using the

following pattern : \\SERVER\SHARE\FOLDER**:

Click now on the button Launch to run Phase Manager.

• If you need to, feel free to contact our customer support at support@projetlineaire.com